




Experiments 1, 2, and 3 (with Ground-Truth Marker-Based Motion Capture)

This folder contains the benchmarking implementation using data collected from Experiments 1, 2, and 3 in [the paper](#).

Data

Data from Experiments 1, 2, and 3 can be downloaded from the [I-MOVE-23](#) webpage.

Follow the directory tree in [imu_benchmark/data/README.md](#) to run the code properly.

Run the Code

Set path

Set `PYTHONPATH`.

```
export PYTHONPATH=$PYTHONPATH:/path/to/imu_benchmark
```

Synchronize data

Run `synchronizer.py` to obtain sync indices between IMU and mocap data.

```
python imu_benchmark/synchronizer.py [--subject SUBJECT] [--task TASK] [--do_mvn]
```

The code will run for all subjects (or tasks) if `subject` (or `task`) is not specified. Set `do_mvn` to process data collected with the MVN Analyze software (from **Experiment 3**).

Get IK

Run `main_ik.py` to obtain IMU (constrained if `do_opensense` is set, otherwise direct) and marker-based kinematics (for **Experiment 1**).

```
python imu_benchmark/main_ik.py [--selected_setup SELECTED_SETUP] [--f_type F_TYPE] [--dim DIM] [--do_mocap] [--do_mvn] [--do_opensense] [--subject SUBJECT] [--task TASK]
```

- Use `mm` for mid placements of IMUs on thighs and shanks.
- Use `vqf`, `xsens`, `ekf`, `mad`, `mah`, or `riann` for `f_type`.
- To use magnetometer information, set `9d` for `dim`, otherwise, `6d`.
- Set `do_mocap` to get marker-based kinematics instead. Of note, no IMU kinematics will be obtained if this is set.
- Set `do_opensense` to run constrained IMU kinematics with OpenSense.

Similarly, run `main_ik_long.py` (for **Experiment 2**) and `main_ik_mvn.py` (for **Experiment 3**).

Evaluate IK

Run `eval.py` to evaluate IMU kinematics using marker-based kinematics as the ground truth.

```
python imu_benchmark/eval.py [--f_type F_TYPE] [--dim DIM] [--reference REFERENCE] [--selected_setup SELECTED_SETUP] [--enable_opensense] [--subject SUBJECT] [--task TASK] [--enable_mocap_alignment] [--enable_psa]
```

- (Always) set `enable_mocap_alignment` to align IMU and marker-based kinematics before evaluation.
- Set `enable_psa` to evaluate kinematics obtained from the static calibration instead of functional calibration (as default).

Similarly, run `eval_long.py` (for **Experiment 2**) and `eval_mvn.py` (for **Experiment 3**).

Visualization

See `README.md` in the `outputs` folder to ensure to ensure that the data are formatted appropriately before plotting them.

If you do not wish obtain **outputs** from running the scripts above, you can also download the folder from FigShare and format it following the mentioned **README.md** file for visualization.

Run **plot_benchmark_f<*>.py** files to plot figures, in which **<*>** stands for the figure index to be plotted. For example,

```
python imu_benchmark/plot_benchmark_f3.py
```